

US EPA ARCHIVE DOCUMENT

HOWNER_OPERATOR5

| | | | | | | | | | | | | | | | |
|-----------------------------|---|---|--------|---|--|---|-----------|---|-------------|---|--------------|---|------------------------|---|-----------|
| Business Rules | <ul style="list-style-type: none"> • User must be the implementer of record for Handler information. • Handler ID, Activity Location, Source Type, and Sequence Number must exist in HHANDLER5. • Handler ID, Activity Location, Source Type, Sequence Number, and Owner/Operator Sequence Number must be unique. • Use of the HOWNER_OPERATOR5 table is mandatory. | | | | | | | | | | | | | | |
| English Name | EPA Handler ID (Primary Key) | | | | | | | | | | | | | | |
| Description | Unique RCRA identification number assigned by the implementing State or Region to each RCRA site (e.g., generators; transporters; and treatment, storage, disposal facilities). | | | | | | | | | | | | | | |
| Data Type and Length | VARCHAR2 (12) | | | | | | | | | | | | | | |
| Allowed Values | Valid ID as outlined below: The ID can be a minimum of 4 characters and a maximum of 12 characters. The first two characters must be a valid state postal code which corresponds to the state in which the handler is located. Spaces are not allowed. | | | | | | | | | | | | | | |
| Default Value | | | | | | | | | | | | | | | |
| Notes | Handlers associated with Navajo Nation should be assigned Handler IDs beginning with 'NN' regardless of where the handler is physically located. | | | | | | | | | | | | | | |
| English Name | Activity Location (Primary Key) | | | | | | | | | | | | | | |
| Description | Indicates the location of the agency regulating the handler. | | | | | | | | | | | | | | |
| Data Type and Length | CHAR (2) | | | | | | | | | | | | | | |
| Allowed Values | State postal code | | | | | | | | | | | | | | |
| Default Value | Location associated with the current user ID. | | | | | | | | | | | | | | |
| Notes | For a list of valid state postal codes, refer to the Column Information Report for LU_STATE. | | | | | | | | | | | | | | |
| English Name | Source Type (Primary Key) | | | | | | | | | | | | | | |
| Description | Code indicating the source of information for the associated data (activity, wastes, etc.). | | | | | | | | | | | | | | |
| Data Type and Length | CHAR (1) | | | | | | | | | | | | | | |
| Allowed Values | <table style="border: none; padding-left: 0;"> <tr><td>A</td><td>Part A</td></tr> <tr><td>B</td><td>Annual/Biennial Report updated with Notification</td></tr> <tr><td>E</td><td>Emergency</td></tr> <tr><td>I</td><td>Implementer</td></tr> <tr><td>N</td><td>Notification</td></tr> <tr><td>R</td><td>Annual/Biennial Report</td></tr> <tr><td>T</td><td>Temporary</td></tr> </table> | A | Part A | B | Annual/Biennial Report updated with Notification | E | Emergency | I | Implementer | N | Notification | R | Annual/Biennial Report | T | Temporary |
| A | Part A | | | | | | | | | | | | | | |
| B | Annual/Biennial Report updated with Notification | | | | | | | | | | | | | | |
| E | Emergency | | | | | | | | | | | | | | |
| I | Implementer | | | | | | | | | | | | | | |
| N | Notification | | | | | | | | | | | | | | |
| R | Annual/Biennial Report | | | | | | | | | | | | | | |
| T | Temporary | | | | | | | | | | | | | | |
| Default Value | | | | | | | | | | | | | | | |
| Notes | If the BR Report Cycle >= 2009 then the Source Type must equal 'B'. | | | | | | | | | | | | | | |
| English Name | Handler Sequence Number (Primary Key) | | | | | | | | | | | | | | |
| Description | Sequence number for each source record about a handler. | | | | | | | | | | | | | | |
| Data Type and Length | NUMBER (6.0) | | | | | | | | | | | | | | |

HOWNER_OPERATOR5

Allowed Values 1 - 999999
Default Value

English Name Owner/Operator Sequence Number (**Primary Key**)
Description Sequential number used to order multiple occurrences of owners and operators.
Data Type and Length NUMBER (4.0)
Allowed Values 1 - 9999
Default Value

English Name Owner/Operator Indicator
Description Code indicating whether the data is associated with a current or previous owner or operator. The system will allow multiple current owners and operators.
Data Type and Length CHAR (2)
Allowed Values
 CO Current owner
 CP Current operator
 PO Previous owner
 PP Previous operator
Default Value
Notes If the Receive Date >= 1/1/2004 then the Owner/Operator Indicator cannot equal 'PO' - Previous owner or 'PP' - Previous operator.

English Name Owner/Operator Type
Description Owner Type: Code indicating the type of entity that legally owns the facility.
 Operator Type: Code indicating the type of entity that is responsible for the overall operation of the facility.
Data Type and Length CHAR (1)
Allowed Values
 C County
 D District
 F Federal
 I Tribal
 M Municipal
 O Other
 P Private
 S State
Default Value

HOWNER_OPERATOR5

| | |
|-----------------------------|--|
| English Name | Owner/Operator Name |
| Description | Owner Name: The name of the entity (individual, agency, or corporation) having legal ownership of the physical operation. The owner name may or may not be the same as the actual site name or the operator name. Operator Name: The name of the entity (individual, agency, or corporation) that is responsible for the overall operation of the facility. The operator name may or may not be the same as the actual site name or the owner name. |
| Data Type and Length | VARCHAR2 (40) |
| Allowed Values | Any non-blank value |
| Default Value | |
| English Name | Date Became Current |
| Description | Date indicating when the owner/operator became current. |
| Data Type and Length | DATE |
| Allowed Values | Valid date greater than or equal to January 1, 1600 in MM/DD/YYYY format blank Not provided |
| Default Value | blank |
| Notes | If the Receive Date >= 1/1/2004 then the Date Became Current must be provided. |
| English Name | Date Ended Current |
| Description | Date indicating when the owner/operator changed to a different owner/operator. |
| Data Type and Length | DATE |
| Allowed Values | Valid date greater than or equal to the Date Became Current in MM/DD/YYYY format blank Not provided |
| Default Value | blank |
| Notes | When entering a new owner/operator, any previous owners/operators that are no longer current should be updated to include a Date Ended Current. |
| English Name | Owner/Operator Street Number |
| Description | The street number from the address of the facility owner or operator. |
| Data Type and Length | VARCHAR2 (12) |
| Allowed Values | Any value blank Not provided |
| Default Value | blank |

HOWNER_OPERATOR5

English Name Owner/Operator Street 1
Description First line of the street address or post office box number of the facility owner or operator.
Data Type and Length VARCHAR2 (30)
Allowed Values Any value
 blank Not provided
Default Value blank

English Name Owner/Operator Street 2
Description Second line of the street address or post office box number of the facility owner or operator.
Data Type and Length VARCHAR2 (30)
Allowed Values Any value
 blank Not provided
Default Value blank

English Name Owner/Operator City
Description The city or town in the address of the facility owner or operator.
Data Type and Length VARCHAR2 (25)
Allowed Values Any value
 blank Not provided
Default Value blank

English Name Owner/Operator State
Description The state code in the address of the facility owner or operator.
Data Type and Length CHAR (2)
Allowed Values If Owner/Operator Country <> US or blank then State code in LU_FOREIGN_STATE
 If Owner/Operator Country = US or blank then State postal code in LU_STATE
 blank Not provided
Default Value blank
Notes For a list of valid state codes, refer to the Column Information Report for LU_STATE and LU_FOREIGN_STATE.

HOWNER_OPERATOR5

English Name Owner/Operator Zip Code
Description Zip code in the address of the owner or operator.
Data Type and Length VARCHAR2 (14)
Allowed Values Any value
 blank Not provided
Default Value blank

English Name Owner/Operator Country
Description The country code in the address of the facility owner or operator.
Data Type and Length CHAR (2)
Allowed Values Country code in LU_COUNTRY
 US United States
 blank US (United States)
Default Value US
Notes For a list of valid country codes, refer to the Column Information Report for LU_COUNTRY.

 If Country is blank, then a value of 'US' will be assumed.

English Name Owner/Operator Telephone Number
Description Telephone number associated with the owner or operator.
Data Type and Length VARCHAR2 (15)
Allowed Values Any value
 blank Not provided
Default Value blank
Notes Telephone number can include space, parentheses and hyphen.

English Name User ID of Last Change
Description Records the user ID of the last person to change the data.
Data Type and Length VARCHAR2 (6)
Allowed Values Valid user ID
Default Value Current user ID

HOWNER_OPERATOR5

| | |
|-----------------------------|--|
| English Name | Date of Last Change |
| Description | Records the date that the data was last changed. |
| Data Type and Length | DATE |
| Allowed Values | Valid date/time stamp |
| Default Value | Current date and time |

| | |
|-----------------------------|--|
| English Name | Notes |
| Description | Additional information regarding the owner/operator. |
| Data Type and Length | VARCHAR2 (2000) |
| Allowed Values | Any value blank Not provided |
| Default Value | blank |

*** End of Report ***